

# PrintMusic Chord Numbers

Maj 1	min 2	aug 3	dim 4	7 5	min7 6	sus4 7	Maj6 8	m7(#5) 9
aug7 10	o 11	o7 12	Maj7 13	9 14	13 15	7(#11) 16	7(b9) 17	+ 18
11 19	m7(b5) 20	dim7 21	min6 22	6 23	min6 24	m 25	M7 26	m7 27
M6 28	m6 29	(add9) 30	(add2) 31	M7(b5) 32	7(#5) 33	M7(#11) 34	M9(b5) 35	M9(#11) 36
M13 37	M13(b5) 38	M13(#11) 39	m(add2) 40	m(add9) 41	m9 42	m11 43	m13 44	m(maj7) 45
m9(maj7) 46	m7(add4) 47	m7(add11) 48	7sus4 49	7(b5) 50	7(#9) 51	7(b5b9) 52	7(b5#9) 53	9sus4 54
9(b5) 55	9(#11) 56	13sus4 57	13(b5) 58	13(b9) 59	13(#9) 60	13(#11) 61	6 62	M9 63
∅ 64	△ 65	7b13 66	7b9 67	7#9 68	b13 #9 69	b13 b9 70	13 71	7#11 72
7sus2 73	13sus 74	9(#5) 75	7#9 #5 76	7sus(b9) 77	13sus(b9) 78	7b9 #5 79	7b9 #11 80	7b9 #11 81
b13 7b9 82	2 83	sus2 84	M 85	M7(+5) 86	M9(+5) 87	(omit5) 88	+7 89	+7(b9) 90
+7(#9) 91	+9 92	(omit3) 93	alt 94	(no3rd) 95	(no5th) 96	-7 97	- 98	-7(b5) 99
-9(b5) 100	-11(b5) 101	△7 102	△7+5 103	△7#11 104	△13 105	-13 106	-11 107	△9 108
△7+4 109	△7+11 110	△7b5 111	7+4 112	7+11 113	7+9 114	△7sus4 115	△7sus2 116	+4 △+5 117
7sus4-3 118	b13 7b9 119	△+5 120	(b13) #9 121	(b13) #9 122	b13 #9 123	(b13) b9 124	(b13) b9 125	b13 b9 126
7(#9) #5 127	7(b9) #5 128	7(#11) b9 129	7(#11) b9 130	7#11 b9 131	7(#11) #9 132	7(#11) #9 133	7#11 #9 134	7(b13) b9 135
7(b13) b9 136	7b13 b9 137	<p>To enter chords using these numeric codes, type the root, then a colon, then the number. Example: for Eb7(#9) type <b>Eb:51</b></p>						