## CORRECTING THE UKULELE TAB

The problem with the Ukulele TAB is that it's upside down. If you enter G-C-E-A in the notation staff, and drag it to the TAB staff, it shows the strings in reverse order, with the G going in on the first string, and the A on the fourth.

If you follow the steps and look at the pictures I've posted, you can turn it over so it's correct.

Open a new document, and with the setup wizard, include the Uke and the Uke TAB staves.

Open the Score Manager, from the Window menu. It will appear as in the picture below. Click on the second staff, which is the TAB. Look in the lower right. It will say Notation Style: Tablature. Click the button next to it, Settings...

	Manager Instrument List		
	Sound Prg   Ba lylon Guitar 2 25 1 lylon Guitar 25 1	nk   Ch   P	erc MIDI Map
	$\mathbf{N}$		
Add Instrument   Score Order: Orchestral	•		Customize View
# Staff Settings for Selected Instrument			
Full Name Ukulele	Notation Style:	Tablature	Settings
		Color Noteheads	Settings
Abbr Name Hir			
Abbr. Name Uk.	Transposition:	None	:)
	Transposition: Staff:	None Other	+) 1)
	Staff:	Other	


On the next screen, Tablature Staff Attributes, click the button that says Edit Instruments.

	Tablature Staff Attributes			
Instrument:	Ukulele Cdit Instruments			
Default Lowest Fret:	0			
Capo Position:	0			
Options:	Show Tuplets			
	Show Clef Only On First Measure			
Fret Numbers				
Vertical Offset:	-0.05556 Inches ‡			
Appearance:	Use Letters			
	🗹 Break Tablature Lines At Numbers			
On "OK" , Reset Staff's Attributes To Tablature Defaults				
?	Cancel OK			

In the Fretboard Instrument Definition, notice the MIDI pitches for the strings: 67, 60, 64, and 69. They need to be reversed. Write them down, and re-enter them in reverse order , as shown below. After you've done this, OK your way back out.

Fretboard Instrument Definition			
Available: Ukulele	\$	New	
Name: Ukulele		Duplicate	
Number of Strings: 4 Number of Frets:	19	Delete	
Diatonic Define		Set As Default	
Listen For String: 4 Play All		Speedy Clef	
String Pitch			
1 69			
2 64			
3 60			
4 67			
		Cancel	

Back in your score, enter the notes G-C-E-A. Drag the measure to the TAB staff. It should now be correct, as shown below.



You can erase any notes you've put in, and save the document as a template Then, you will have it correct and ready to go, the next time you want it.